|| Parallels[®]

How to add new Vendors and Atributes to be configured in RAS Radius

• Parallels Remote Application Server 18.1

Symptoms

In order to configure RAS Radius with specific Vendor and add Attributes go to:

RAS Console > *Connection* > *Multi-factor authentication* > *specify Radius* > *Settings* > *Attributes* > *add* > *choose any preconfigured Vendor and Attribute*

In certain scenarios you need to add Vendors and Attributes that are not presented by default.

Resolution

1. Navigate to installation folder of RAS. By default it is C:\Program Files (x86)\Parallels\ApplicationServer\

2. find RadiusAttr.def and open it with any test editor such as Notepad, Notepad ++ and etc.

Vendors section

The vendor section has a count with represents the number of vendors configured.

Each vendor has an ID and a Name as follows.

```
[vendors]
count = 10
0_id=0
0_name=Global
.
3_id=255
3_name=Cisco VPN 5000
.
```

9_id=193 9_name=Ericsson

Vendor Attributes section

Each vendor has a section titled with the corresponding vendor ID.

You can find a count of attributes and then the name and type for each attribute.

Possible attributes are as follows:

0 Numeric

- 1 String
- $2 \, \operatorname{IPv4}$
- 3 Time

```
[255]
count = 2
0_id = 4
0_name = CVPN5000.VPN.GroupInfo
0_type = 1
1_id = 5
1_name = CVPN5000.VPN.Password
1_type = 1
```

Adding Global Attributes

If you require to add global attributes please do the following

1. go to section zero and change the count to the new value required e.g. here we are adding a new attribute:

[0] count = 212. Add the attribute(s) information

20_id = 24 20_name = State 20_type = 1 3. Add the attribute in RAS settings

© 2024 Parallels International GmbH. All rights reserved. Parallels, the Parallels logo and Parallels Desktop are registered trademarks of Parallels International GmbH. All other product and company names and logos are the trademarks or registered trademarks of their respective owners.