

## Appliance does not successfully boot, an error is shown on the VM console

• Parallels Secure Workspace

## **Symptoms**

The appliance does not successfully boot, an error is shown in the VM console.

In certain circumstances, the file system of the appliance might be in trouble (unclean shutdown, file system corruption, ..) which results in the appliance not booting anymore, and users not being able to access the portal/Workspace after a reboot.

This may happen when there was for example a power cut (to the hypervisor) or the appliance had to be shut down in a forceful way.

The most common error on the VM console when an appliance is in this state is similar this:

FileNotFoundError: [Errno 2] No usable temporary directory found in ['/tmp', '/var/tmp', '/usr/tmp', '/']

```
age.py', 'persist_ip_address']' returned non-zero exit status 1
During handling of the above exception, another exception occurr
Traceback (most recent call last):
  File "/root/bootscript.py", line 495, in <module>
    persist_ip_address()
  File "/root/bootscript.py", line 459, in persist_ip_address
    raise PersistIPFailed()
__main__.PersistIPFailed
During handling of the above exception, another exception occurs
Traceback (most recent call last):
  File "/root/bootscript.py", line 502, in <module>
    include_traceback=False)
  File "/root/bootscript.py", line 490, in show_exc
    d.msgbox(message, width=WIDTH, height=HEIGHT)
  File "/usr/lib/python3.5/dist-packages/dialog.py", line 3028,
    kwargs)
  File "/usr/lib/python3.5/dist-packages/dialog.py", line 1717,
    code, output = self._perform(args, **kwargs)
  File "/usr/lib/python3.5/dist-packages/dialog.py", line 1501,
    **kwargs)
  File "/usr/lib/python3.5/dist-packages/dialog.py", line 1290, mode="w", prefix="pythondialog.tmp", delete=False)
  File "/usr/lib/python3.5/tempfile.py", line 679, in NamedTempo
prefix, suffix, dir, output_type = _sanitize_params(prefix,
  File "/usr/lib/python3.5/tempfile.py", line 269, in _sanitize.
    dir = gettempdir()
  File "/usr/lib/python3.5/tempfile.py", line 435, in gettempdim
    tempdir = _get_default_tempdir()
  File "/usr/lib/python3.5/tempfile.py", line 370, in _get_defau
    dirlist)
FileNotFoundError: [Errno 2] No usable temporary directory found
 '/'1
```

## Cause


Disk corruption occurred, highly likely because the machine was shut down in an improper way.

## Resolution

This guide will focus on VMware ESXi but the procedure is almost the same for every hypervisor, except for how to load the virtual disk to boot from.

This guide will also help to resolve other ESX4-fs errors which may be shown in the VM console


- 1. Download an **Ubuntu Desktop** ISO: <a href="https://ubuntu.com/download/desktop">https://ubuntu.com/download/desktop</a>
  This guide will use the Parted GUI so that's why we download the desktop release of Ubuntu.
- 2. Store the ISO on an ESXi datastore.
- 3. Open the **Edit settings** dialog on ESXi to edit the appliance VM. Click on **Add another device** and select **CD/DVD drive**.
- 4. Once the virtual CD drive has been added, open the drop-down menu of the New CD/DVD Drive and select **Datastore ISO file**. A dialog will appear to select the Ubuntu Desktop ISO from the data store you saved it to, if not select [**Browse**] and find the Ubuntu ISO. Make sure the option **Connect at power on** is checked.




- 5. In the same dialog window, navigate to **VM Options > Boot Options** and tick the checkbox for **Force BIOS setup**.
- 6. Start the VM so it will enter the BIOS: under **boot** make the CD-ROM drive the first device to boot from. Exit the BIOS and save the changes.

Save


- 7. Once the Ubuntu Desktop ISO has booted, select **Try Ubuntu**. This will launch a full Ubuntu Desktop.
- 8. Once the desktop is booted, start **GParted Partition Editor.** Right-click the /dev/sda1 partition and choose **Check**.



9. The file system check is now queued, select **Apply all operations** to execute the check.



10. The pending operations will now be applied and the file system will be repaired. You can view the report on what has been repaired on the file system.



- 11. Shut down the appliance, edit the VM again. Disconnect the CD/DVD Drive 1. Otherwise, the VM will boot again from the Ubuntu Desktop ISO.
- 12. Start your appliance again. If the repair went well, it should boot normally. If not, contact the support team.

© 2024 Parallels International GmbH. All rights reserved. Parallels, the Parallels logo and Parallels Desktop are registered trademarks of Parallels International GmbH. All other product and company names and logos are the trademarks or registered trademarks of their respective owners.