



How to share Internet connection from Windows Virtual Machine to Mac OS?

- Parallels Desktop for Mac Standard Edition
- Parallels Desktop for Mac Pro Edition
- Parallels Desktop for Mac Business Edition

I have a device that allows connection to the Internet, but it only has drivers for Windows. How can I share the Internet connection from Windows Virtual Machine to macOS?

Resolution

Note: the solution below won't work on Mac computers with Apple silicon and Mac computers with Intel processors having macOS Ventura and newer installed as a host operating system.

This article lists basic steps to configure your Mac to share Network Connection from Windows. Please note that it is not implemented in Parallels Desktop for Mac and settings may vary on some specific configuration.

Due to this, Parallels Technical support does not provide any assistance with this implementation and you can use it and modify as much as you like to fit your needs or your configuration. Any related questions can be asked in the corresponding thread of the [Parallels Forum](#).

Instructions:

1. Connect the modem to USB port on Mac OS X computer
2. Start Parallels Desktop (do not launch the virtual machine yet) and open Parallels Desktop menu on the menubar > **Preferences** > **Network** > **Host Only** tab:
3. Fill both **Start address** and **End address** with the numbers below:

```
Start address [192.168.0.128]
End address [192.168.0.254]
```

It should look like this:

4. Make Parallels Network Adapter visible in Mac OS X Network Preferences by following the steps in [KB 116528](#).
5. Go to Mac OS X **System Preferences** > **Network**, choose **Parallels Host-Only** adapter and change the settings to be:

```
Router: 192.168.0.1
```

Click **Advanced** > choose **DNS** > then click the "+" symbol and add the address below, then **OK** to apply.

```
DNS server: 192.168.0.1
```

6. Start the virtual machine, go to the **Parallels Desktop** dropdown menu > **Devices** > **Network** > change network connection type to **Host-Only Network**.

7. Connect your USB modem to virtual machine. For this purpose click on the **Parallels Desktop** menu > **Devices** > **External Devices** and check the necessary modem.

If there are no drivers installed yet for this USB modem device, please install them first. Refer to the manual of the device for additional information.

8. When modem installation is completed, a new **Network connection** should appear under **Start** > **Settings** > **Network** > **Network and Sharing Center/Network Connections** applet.

Click (or right-click) the correspondent USB device network connection and choose **Properties** > **Sharing**.

Enable **Allow other network users to connect through this computer's Internet connection**. In the **Home networking connection** drop-down list, select the network adapter which was previously set to **Host-only**.

9. Then get back to

◆ **Settings** > **Network** > **Change adapter options**

◆ Right-click on the network connection created for **Host-only** in Windows > **Properties**

◆ **Internet Protocol version 4 (TCP/IPv4) > Properties**

◆ In **General Tab** > select **Use the following IP address** and change the IP to be:

© 2024 Parallels International GmbH. All rights reserved. Parallels, the Parallels logo and Parallels Desktop are registered trademarks of Parallels International GmbH. All other product and company names and logos are the trademarks or registered trademarks of their respective owners.