

## Running a complete Windows 11 for Arm installation process with OOBE on Mac computers with M-series chips

- Parallels Desktop for Mac Standard Edition
- Parallels Desktop for Mac Pro Edition
- Parallels Desktop for Mac Business Edition

The easiest way to install Windows 11 for Arm on Parallels Desktop for Mac is to launch the Installation Assistant and follow the Get Windows 11 from Microsoft automated procedure. However, if you want to fine-tune your setup during the installation process, you may follow the manual procedure that will not skip Microsoft's Out of the Box Experience, also known as OOBE. OOBE procedure lets you change language and regional settings, enter an existing product key, select OS edition, log in with your Microsoft account, adjust your privacy settings, switch to the Audit mode, and more.

To complete the OOBE process manually during the installation, follow these steps:

- 1. Download a Windows 11 for Arm ISO image.
  - a. Most users will be best served by the **Get Windows 11 from Microsoft** option to download the ISO image as described <u>here</u>, interrupting the process once the image is downloaded. The ISO image can then be found in the ~/Downloads folder.
  - b. Corporate users can find the image on Microsoft's Business portal, as shown on the image below.

2. Open the Parallels Desktop Control Center and click on the "+" button in the top right corner. This will launch the Installation Assistant.
3. Under Create New, select the Install Windows from a DVD or image file option.

4. On the next page, allow the system to automatically locate the ISO installation image or use the <b>Choose</b>
Manually button to find it. Make sure to check the Install operating system manually box and click Continue.
<ol><li>Follow the subsequent steps as directed. The complete OOBE process will launch during the Windows 11 for Arm installation.</li></ol>

© 2024 Parallels International GmbH. All rights reserved. Parallels, the Parallels logo and Parallels Desktop are registered trademarks of Parallels International GmbH. All other product and company names and logos are the trademarks or registered trademarks of their respective owners.