

Mouse synchronization and screen resize do not work

- Parallels Desktop for Mac Standard Edition
- Parallels Desktop

Symptoms

Mouse synchronization does not work and you need to press **Ctrl+Alt** to release the mouse or dynamic screen resolution does not work when the size of Virtual Machine window is changed.

In device manager you can see Intel(R) 82815 Processor to AGP controller-1131 within System devices with exclamation mark, Display Adapter is missing among devices.

Cause

Emulated video adapter was recognized as device with AGP interface instead of PCI interface.

Resolution

- 1. Right-click on Intel(R) 82815 Processor to AGP controller-1131, in the drop down menu choose Update driver.
- 2. In the Hardware Update Wizard window choose, No, not this time --> Install from a list or a list or specific

bridge in the list hardware devices:	
3.Click Next. Accept the prompt to reboot the windows.4. After reboot Video Controller (VGA compatible) with exclamation mark should appear in device management.	ınager.
5. Right click on Video Controller> Update driver> In the Hardware Update Wizard window choose No,not this time> Install from a list or a list or specific location (Advanced)> Don't searce choose the driver to install> choose Display adapters in the list of hardware type:	ch. I will
6. In the next Hardware Update Wizard window click " Have Disk " button> browse and locate " C:\P Files\Parallels\Parallels Tools\Drivers\prl_va\prl_va.inf"	rogram
7. Click Open > Next . Follow the prompt to reboot the windows.	
Note: After Windows is rebooted all features like <i>dynamic screen resolution</i> , <i>automatic mouse capture</i> and <i>Coherence</i> will work in your virtual machine.	

2024 Parallels International GmbH. All rights reserved. Parallels, the Parallels logo and Parallels Deslistered trademarks of Parallels International GmbH. All other product and company names and logos lemarks or registered trademarks of their respective owners.	ktop are are the